# **Sport Video Tracking System**

# **Description**

This project is a video tracking system for sports, utilizing stereo cameras to track athletes' movements in real-time. Camera calibration is an essential step to ensure optimal tracking accuracy.

### **Features**

- **Real-Time Tracking**: Precise tracking of athletes during sports sessions.
- **Camera Calibration**: Uses a chessboard pattern to calibrate stereo cameras.
- **User-Friendly Interface**: Instructions and visual feedback to facilitate usage.
- **Movement Analysis**: Tools to analyze athletes' movements.

### **Prerequisites**

- Python 3.x
- OpenCV
- Numpy
- Mediapipe
- Pygame

### Installation

1. Install the required packages:

```
pip install -r requirements.txt
```

# **Usage**

#### **Camera Calibration**

You have the possibility, if you use 2 cameras, to calbirate them.


#### 1. Prerequisites

- chessboard
- settings of your camera :you need to change the ID of your cameras, the size
  of your chessboard, the image resolution and the size of each side of the
  squares of the chessboard.


```
calibration_settings = {
  'camera0': 2,
  'camera1': 1,
  'frame_width': 1280,
  'frame_height': 720,
  'mono_calibration_frames': 10,
  'stereo_calibration_frames': 10,
  'view_resize': 1,
  'checkerboard_box_size_scale': 2.2,
  'checkerboard_rows': 7,
  'checkerboard_columns': 7,
  'cooldown': 100
}
```

### 2. Calibration of each camera


- For both cameras, you must first take turns presenting the board (camera 1 then 2). For each camera, **10 frames** will be captured every 100ms. To start capturing, **press the space bar.** 




- After capturing the frames, you must **validate** or not the images (by pressing **space to validate or S to skip**).



- Then, you need to calibrate **both cameras at the same time**. Make sure they are in their **final positions** and that the board is clearly visible to both. Press the **space bar to begin**.



Finally, as before, validate or not the images by pressing space or S (note that this validates the image pair)



### **Video Tracking**

1. Run the Tracking Script:

python main.py

2. **Start Tracking:** You will have several choices: - The number of camera (1 or 2). - The type of sports (1 = curl, 2 = squats). - The possibility to calibrate the cameras. - Indicate the number of sets and repetitions.